

Indoor Air Quality 2nd Gen. Library Documentation

Contents


1	ZMOD4410 Application Programming Interface Overview	1
2	How to Read Library Version	2
3	How to Work with the Renesas Gas Algorithm Libraries	3
4	Example for zmod4xxx_cleaning:	4
5	Module Index	5
5.1	Modules	5
6	Data Structure Index	6
6.1	Data Structures	6
7	File Index	7
7.1	File List	7
8	Module Documentation	8
8.1	Return codes of the algorithm functions.	8
8.1.1	Detailed Description	8
8.1.2	Macro Definition Documentation	8
8.1.2.1	IAQ_2ND_GEN_OK	8
8.1.2.2	IAQ_2ND_GEN_STABILIZATION	8

9	Data Structure Documentation	9
9.1	algorithm_version Struct Reference	9
9.1.1	Detailed Description	9
9.2	iaq_2nd_gen_handle_t Struct Reference	9
9.2.1	Detailed Description	10
9.2.2	Field Documentation	10
9.2.2.1	log_rcda	10
9.2.2.2	stabilization_sample	10
9.3	iaq_2nd_gen_results_t Struct Reference	10
9.3.1	Detailed Description	11
9.3.2	Field Documentation	11
9.3.2.1	eco2	11
9.3.2.2	etoh	11
9.3.2.3	iaq	11
9.3.2.4	log_rcda	11
9.3.2.5	rmox	11
9.3.2.6	tvoc	11
10	File Documentation	12
10.1	iaq_2nd_gen.h File Reference	12
10.1.1	Detailed Description	13
10.1.2	Function Documentation	13
10.1.2.1	calc_iaq_2nd_gen()	13
10.1.2.2	init_iaq_2nd_gen()	13
10.2	zmod4xxx_cleaning.h File Reference	14
10.2.1	Detailed Description	14
10.2.2	Function Documentation	14
10.2.2.1	zmod4xxx_cleaning_run()	14

Chapter 1

ZMOD4410 Application Programming Interface Overview

This document describes the libraries for the ZMOD4410 gas sensor module using the second generation algorithms for indoor air quality measurements (IAQ 2nd Gen). This algorithm is the recommended for accurate and consistent TVOC, IAQ and eCO2 measurements. Refer to the *ZMOD4410 Programming Manual - Read Me* for further information regarding sample code. The figure below shows an overview of the ZMOD4xxx API, programming example and libraries. Custom microcontrollers can be used to establish I2C communication. Using the user's own microcontroller requires implementing the user's own target-specific I2C and low-level functions (highlighted in blue). The following sections describe in detail the IAQ 2nd Gen algorithm libraries and an optional cleaning procedure after product assembly.



Chapter 2

How to Read Library Version

Libraries have library version as variable that can be accessed during run-time.

To access the library version;

```
#include <iaq_2nd_gen.h>

extern algorithm_version iaq_2nd_gen_ver;

int main()
{
    int8_t ret;
    zmod4xxx_dev_t dev;

    /* Sensor target variables */
    uint8_t zmod4xxx_status;
    .
    .

    // Debug library version
    printf("major = %u", iaq_2nd_gen_ver.major);
    printf("minor = %u", iaq_2nd_gen_ver.minor);
    printf("patch = %u", iaq_2nd_gen_ver.patch);
}
```

Chapter 3

How to Work with the Renesas Gas Algorithm Libraries

- Include the intended header file in the user's program for gas sensor module control; for example:
`#include "iaq_2nd_gen.h"`
- Copy the library file into user's project folder
- Call the intended function in the user's program

Example for IAQ:

```
#include "iaq_2nd_gen.h"

int main() {
    int8_t ret;
    iaq_2nd_gen_handle_t iaq_handle;
    iaq_2nd_gen_results_t results;
    zmod4xxx_dev_t dev;

    // User's functionality
    // Hardware initialization

    ret = init_iaq_2nd_gen(&iaq_handle);

    // User's functionality

    while(1) {
        // get sensor results with API
        ret = calc_iaq_2nd_gen(&iaq_handle, &dev, &sensor_results, &results);
    }

    return 0;
}
```

Chapter 4

Example for zmod4xxx_cleaning:

- Include the intended header file in the user's program for cleaning;
`#include "zmod4xxx_cleaning.h"`
- Copy the library file into user's project folder
- Call the `zmod4xxx_cleaning_run` function in the user's program
- IMPORTANT NOTE : The cleaning procedure can be run only once during the modules lifetime and takes 10 minutes.

```
#include "zmod4xxx_cleaning.h"

int main() {
    // initialization of the device structure(dev)
    zmod4xxx_dev_t dev;

    // User's functionality

    zmod4xxx_cleaning_run(&dev);

    // User's functionality

    return 0;
}
```

Chapter 5

Module Index

5.1 Modules

Here is a list of all modules:

Return codes of the algorithm functions. 8

Chapter 6

Data Structure Index

6.1 Data Structures

Here are the data structures with brief descriptions:

algorithm_version	Variables that describe the library version	9
iaq_2nd_gen_handle_t	Variables that describe the sensor or the algorithm state	9
iaq_2nd_gen_results_t	Variables that receive the algorithm outputs	10

Chapter 7

File Index

7.1 File List

Here is a list of all documented files with brief descriptions:

iaq_2nd_gen.h	This file contains the data structure definitions and the function definitions for the 2nd generation IAQ algorithm	12
zmod4xxx_cleaning.h	This file contains the cleaning function definition for ZMOD4xxx	14

Chapter 8

Module Documentation

8.1 Return codes of the algorithm functions.

Macros

- `#define IAQ_2ND_GEN_OK (0)`
- `#define IAQ_2ND_GEN_STABILIZATION (1)`

8.1.1 Detailed Description

8.1.2 Macro Definition Documentation

8.1.2.1 IAQ_2ND_GEN_OK

```
#define IAQ_2ND_GEN_OK (0)
```

everything okay

8.1.2.2 IAQ_2ND_GEN_STABILIZATION

```
#define IAQ_2ND_GEN_STABILIZATION (1)
```

sensor in stabilization

Chapter 9

Data Structure Documentation

9.1 `algorithm_version` Struct Reference

Variables that describe the library version.

```
#include <iaq_2nd_gen.h>
```

Data Fields

- `uint8_t major`
- `uint8_t minor`
- `uint8_t patch`

9.1.1 Detailed Description

Variables that describe the library version.

The documentation for this struct was generated from the following file:

- [iaq_2nd_gen.h](#)

9.2 `iaq_2nd_gen_handle_t` Struct Reference

Variables that describe the sensor or the algorithm state.

```
#include <iaq_2nd_gen.h>
```

Data Fields

- float [log_rcda](#) [9]
- uint8_t [stabilization_sample](#)
- uint8_t [need_filter_init](#)
- float [tvoc_smooth](#)
- float [tvoc_deltafilter](#)
- float [acchw](#)
- float [accow](#)
- float [etoh](#)
- float [tvoc](#)
- float [eco2](#)
- float [iaq](#)

9.2.1 Detailed Description

Variables that describe the sensor or the algorithm state.

9.2.2 Field Documentation

9.2.2.1 [log_rcda](#)

```
float log_rcda[9]
```

log10 of CDA resistances.

9.2.2.2 [stabilization_sample](#)

```
uint8_t stabilization_sample
```

Number of remaining stabilization samples.

The documentation for this struct was generated from the following file:

- [iaq_2nd_gen.h](#)

9.3 [iaq_2nd_gen_results_t](#) Struct Reference

Variables that receive the algorithm outputs.

```
#include <iaq_2nd_gen.h>
```

Data Fields

- float [rmox](#) [13]
- float [log_rcda](#)
- float [iaq](#)
- float [tvoc](#)
- float [etoh](#)
- float [eco2](#)

9.3.1 Detailed Description

Variables that receive the algorithm outputs.

9.3.2 Field Documentation

9.3.2.1 `eco2`

```
float eco2
```

eCO2 concentration (ppm).

9.3.2.2 `etoh`

```
float etoh
```

EtOH concentration (ppm).

9.3.2.3 `iaq`

```
float iaq
```

IAQ index.

9.3.2.4 `log_rcda`

```
float log_rcda
```

log10 of CDA resistance.

9.3.2.5 `rmox`

```
float rmox[13]
```

MOx resistance.

9.3.2.6 `tvoc`

```
float tvoc
```

TVOC concentration (mg/m³).

The documentation for this struct was generated from the following file:

- [iaq_2nd_gen.h](#)

Chapter 10

File Documentation

10.1 iaq_2nd_gen.h File Reference

This file contains the data structure definitions and the function definitions for the 2nd generation IAQ algorithm.

```
#include <stdint.h>
#include <math.h>
#include "zmod4xxx_types.h"
```

Data Structures

- struct [algorithm_version](#)
Variables that describe the library version.
- struct [iaq_2nd_gen_handle_t](#)
Variables that describe the sensor or the algorithm state.
- struct [iaq_2nd_gen_results_t](#)
Variables that receive the algorithm outputs.

Macros

- #define [IAQ_2ND_GEN_OK](#) (0)
- #define [IAQ_2ND_GEN_STABILIZATION](#) (1)

Functions

- int8_t [calc_iaq_2nd_gen](#) ([iaq_2nd_gen_handle_t](#) *handle, [zmod4xxx_dev_t](#) *dev, const uint8_t *sensor_↵
results_table, [iaq_2nd_gen_results_t](#) *results)
calculates IAQ results from present sample.
- int8_t [init_iaq_2nd_gen](#) ([iaq_2nd_gen_handle_t](#) *handle)
Initializes the IAQ algorithm.

10.1.1 Detailed Description

This file contains the data structure definitions and the function definitions for the 2nd generation IAQ algorithm.

Author

Renesas Electronics Corporation

Version

2.2.0

The library contains an algorithm to calculate an EtOH, TVOC and IAQ index from ZMOD4410 measurements. The implementation is made to allow more than one sensor.

10.1.2 Function Documentation

10.1.2.1 calc_iaq_2nd_gen()

```
int8_t calc_iaq_2nd_gen (
    iaq_2nd_gen_handle_t * handle,
    zmod4xxx_dev_t * dev,
    const uint8_t * sensor_results_table,
    iaq_2nd_gen_results_t * results )
```

calculates IAQ results from present sample.

Parameters

in	<i>handle</i>	Pointer to algorithm state variable.
in	<i>dev</i>	Pointer to the device.
in	<i>sensor_results_table</i>	Array of 32 bytes with the values from the sensor results table.
out	<i>results</i>	Pointer for storing the algorithm results.

Returns

error code.

10.1.2.2 init_iaq_2nd_gen()

```
int8_t init_iaq_2nd_gen (
    iaq_2nd_gen_handle_t * handle )
```

Initializes the IAQ algorithm.

Parameters

out	handle	Pointer to algorithm state variable.
-----	--------	--------------------------------------

Returns

error code.

10.2 zmod4xxx_cleaning.h File Reference

This file contains the cleaning function definition for ZMOD4xxx.

```
#include "zmod4xxx.h"
```

Functions

- `int8_t zmod4xxx_cleaning_run (zmod4xxx_dev_t *dev)`
Start a cleaning procedure.

10.2.1 Detailed Description

This file contains the cleaning function definition for ZMOD4xxx.

Version

2.4.2

Author

Renesas Electronics Corporation

The library contains the function that starts the cleaning procedure. **The procedure takes 10 minutes.** After successful cleaning, the function returns 0. **The procedure can be run only once.**

10.2.2 Function Documentation

10.2.2.1 zmod4xxx_cleaning_run()

```
int8_t zmod4xxx_cleaning_run (  
    zmod4xxx_dev_t * dev )
```

Start a cleaning procedure.

Parameters

<code>in</code>	<code>dev</code>	pointer to the device
-----------------	------------------	-----------------------

Returns

Error code

Return values

<code>0</code>	Success
<code>!= 0</code>	Error

IMPORTANT NOTICE AND DISCLAIMER

RENESAS ELECTRONICS CORPORATION AND ITS SUBSIDIARIES ("RENESAS") PROVIDES TECHNICAL SPECIFICATIONS AND RELIABILITY DATA (INCLUDING DATASHEETS), DESIGN RESOURCES (INCLUDING REFERENCE DESIGNS), APPLICATION OR OTHER DESIGN ADVICE, WEB TOOLS, SAFETY INFORMATION, AND OTHER RESOURCES "AS IS" AND WITH ALL FAULTS, AND DISCLAIMS ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING, WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT OF THIRD PARTY INTELLECTUAL PROPERTY RIGHTS.

These resources are intended for developers skilled in the art designing with Renesas products. You are solely responsible for (1) selecting the appropriate products for your application, (2) designing, validating, and testing your application, and (3) ensuring your application meets applicable standards, and any other safety, security, or other requirements. These resources are subject to change without notice. Renesas grants you permission to use these resources only for development of an application that uses Renesas products. Other reproduction or use of these resources is strictly prohibited. No license is granted to any other Renesas intellectual property or to any third party intellectual property. Renesas disclaims responsibility for, and you will fully indemnify Renesas and its representatives against, any claims, damages, costs, losses, or liabilities arising out of your use of these resources. Renesas' products are provided only subject to Renesas' Terms and Conditions of Sale or other applicable terms agreed to in writing. No use of any Renesas resources expands or otherwise alters any applicable warranties or warranty disclaimers for these products.

(Rev.1.0 Mar 2020)

Corporate Headquarters

TOYOSU FORESIA, 3-2-24 Toyosu,
Koto-ku, Tokyo 135-0061, Japan
www.renesas.com

Contact Information

For further information on a product, technology, the most up-to-date version of a document, or your nearest sales office, please visit:
www.renesas.com/contact/

Trademarks

Renesas and the Renesas logo are trademarks of Renesas Electronics Corporation. All trademarks and registered trademarks are the property of their respective owners.